Guidelines To The New Soft-Lock & Cloud Licenses

Installation · https://mes100.com/docs/guideline-to-the-new-soft-lock-cloud-licenses/

Starting from **MiTS 2.8** version, we introduce a few more types of licenses to accommodate the new working normal.

We improved upon the previous soft-lock license in 2.5 version, so now that the soft-lock and cloud license no longer depend on the machine hardware ID. The differences between the licenses we introduced are listed below:

Hardlock License	Cloud License	Soft-Lock License
Modules, MiTS1, and MiTS 2	Starting from MiTS 2.8.X.X	Starting from MiTS 2.8.X.X ****Please take note that starting 2.8 version, softlock no longer depends upon your hardware ID****
Requires a physical dongle to be plugged into the USB port of the user's machine to launch the software.	Requires user to login into the Cloud Account on **Virbox User License Tool**	Requires user to login into the Cloud Account on **Virbox User License Tool** and online-bind license to the machine before launching software


For users who **own both a cloud and a soft-lock license**, you may register both licenses under **one single username (email address)**. However, users will need to **set the Cloud License as the default**, following the **steps here** for the software to apply the correct license type.

Temporarily bind to the machine where the dongle is plugged into	Can launch MiTS as long as user is logged into the Cloud Account and **require stable internet connection**	The **first time**, the machine needs to be online so the license can be **bound** to that machine. **After the license has been bound**, the user can launch MiTS **without an internet connection (offline)**
Can be used on other machine to launch software, as long as the dongle is plugged into the USB port of the machine	Can be used to launch software on different machines, but requires the user to be logged out of the Cloud Account on the previous machine first	Can be used on another machine (Machine B) by **online-unbind** the current machine (Machine A) from the license through the Virbox User License Tool, similar to plugging and unplugging the physical dongle from a machine. To launch the software on another machine, users only have to **log in to the account** and **online-bind to the license** again.


License is available for existing and potential users	This type of license is available for MiTS 2 training session and user with trial licences	Just like a normal hardware dongle, but instead of carrying the dongle around, you bind and unbind the

Installation of Virbox User License Tool


1. Download and install MiTS 2.8.x.x version.
2. Together with MiTS 2.8 version, the Virbox User License Tool will be installed as prerequisite.
3. Click "Next" and the installation process of Virbox User License Tool will be started.




4. Click "Accept" for Virbox Software License Agreement



5. Click "Install"



6. Click "Experience" and Virbox User License Tool will launch. Exit Virbox and continue the installation for MiTS 2.8.x.x as usual until the process is finish.




Activation & Deactivation of Cloud License


1. Send newly created or existing email username to MES Support Team.
2. Once a license has been created by MES Support Team, users will receive an email from **Virbox LM** with the initial password that will be used for login purposes.

> Dear users,
> You have been signed up by "MES Innovation Sdn Bhd" Administrator to become a Virbox LM user to use their License System. Please login with your Email, the initial password being XXX. For your account security, please change your password when you login the system
>
> Virbox LM Platform


3. Launch Virbox User License Tool and login into the account using the username and password given.




4. Once logged in, users can launch the software and MiTS should now be able to be used.
5. To check on the license container (type), license status, and license expiration date, users can click on the **number of license**.




6. Double click on the license with name MiTS 2.


Region: International
Version: v2.2.0.51851(2.3.0.51851)
FAQ
Summary
Available
Expired
(International)
All Developers
global search
Cloud/Soft
Dongle
Softwares
Service
Diagnosis
Advance
MiTS 2
090000000000008e
Query/Online/Offline Bind
MiTS 2
090000000000008e
Show: 2/2
(Support Ctrl/Shift Select and Righ-Click Menu)
Filter: All
Cloud
Soft(Unbind)
Soft
Dongle
Net



7. To launch software on another machine, users have to logout from their account on Virbox on the previous machine by clicking "*Cloud/Soft > email username > logout button*" and login on the new machine.




Activation of Soft-Lock License


1. Send newly created or existing email username to MES Support Team.
2. Once a license has been created by MES Support Team, users will receive an email from **Virbox LM** with the initial password that is use for login purposes.

> Dear users,
> You have been signed up by "MES Innovation Sdn Bhd" Administrator to become a Virbox LM user to use their License System. Please login with your Email, the initial password being XXX. For your account security, please change your password when you login the system
>
> Virbox LM Platform


3. Launch Virbox User License Tool and login into the account using the username and password given.




4. Click on the **number of license**.




5. Double click on the license with name MiTS 2.




6. Click "Online-Bind".



7. Once Online-Bind succeeds, click "Close". Launch software and MiTS should now be able to be used.




8. Users can also check on the name and number of machines bound to the license (for users with multiple licenses) by clicking "Bind-Info".


Region: International
Version: v2.2.0.51851(2.3.0.51851)
FAQ
Return
Cloud/Soft
Dongle
Softwares
Service
Diagnosis
Advance
logo
MiTS 2
090000000000008e
License Description
No software description
License Details
License Source:
johndoe@gmail.com
International)
License Container:
Offline(bound)
Bind Info
Online-Bind
Download Offline-Bc
License Status:
Available
Start Date:
2022/01/07 00:00:00
Expired Date:
2022/01/31 23:59:59
First Use Date:
2022/01/07 14:56:26
Time Span:
0Days 0Hours 0Minutes 0Seconds
Remain Times:

Concurrence:


Concurrence Type:
None
more...




9. With a soft-lock license, the initial login to a user's account is a **one-time step**, solely intended to bind the license with the machine. After a successful binding process, users can freely launch the software as usual and even **remain disconnected from the internet for up to 90 days**. There's no need for subsequent logins or logouts as long as the license remains bound to the machine.

Deactivation of Soft-Lock License


1. Launch Virbox User License Tool and login into the account with the username and password.
2. Click "Local Soft".




3. Click on **number of license**.



4. Double click on the license with name MiTS 2.



5. Click "Online-Unbind".



Region: International
Version: v2.2.0.51851(2.3.0.51851)
FAQ
Return
Cloud/Soft
Dongle
Softwares
Service
Diagnosis
Advance
logo
MiTS 2
090000000000008e
License Description
No software description
License Details
License Source:
johndoe@gmail.com
(Account)
License Container:
Offline (Local)
Online-Unbind
Offline-Unbound
License Status:
Available
Start Date:
2022/01/07 00:00:00
Expired Date:
2022/01/31 23:59:59
First Use Date:
2022/01/07 14:56:26
Time Span:

Remain Times:

Concurrence:

Concurrence Type:
Process
more...

6. Click "OK".



7. Once Online-Unbind has succeeded, click "Close". Users can see that now under Local Soft, no available license are tied to the machine.

8. Users can now move to a new machine, and repeat the steps on how to activate the soft-lock license on the new machine.

Related



Ngu Soon Hui

I'm the Benevolent Dictator for Life for MiTS Software cum Editor of this website. Read more here.

You can also contact me at soonhui@mes100.com